TASK/任务	CONDA PACKAGE AND ENVIRONMENT MANAGER COMMAND CONDA包和环境管理 命令
Install a package/安装包	conda install \$PACKAGE_NAME
Update a package/升级一 个包	conda updatename $ENVIRONMENT_NAME {\tt PACKAGE\_NAME}$
Update package manager/ 升级conda自身	conda update conda
Uninstall a package/卸载包	conda removename $ENVIRONMENT_NAME$ PACKAGE_NAME
Create an environment/创建一个新的环境	conda createname \$ENVIRONMENT_NAME python
Activate an environment/ 激活一个新环境	source activate \$ENVIRONMENT_NAME
Deactivate an environment/停用一个环 境	source deactivate
Search available packages/ 搜索可用的包	conda search \$SEARCH_TERM
Install package from specific source/从特殊的源 安装包	conda installchannel $URL$ PACKAGE_NAME
List installed packages/查 看已安装包列表	conda listname \$ENVIRONMENT_NAME
Create requirements file/ 创建需求文件	conda listexport
List all environments/列举 出所有已安装环境	conda infoenvs
Install other package manager/安装其他包管理 软件pip	conda install pip
Install Python/安装python	conda install python=x.x
Update Python/升级 python	conda update python *